

GUROBI

Gurobi Optimization, www.gurobi.com

Contents

1	Introduction	1
2	How to Run a Model with Gurobi	1
3	Overview of GAMS/Gurobi	2
3.1	Linear Programming	2
3.2	Mixed-Integer Programming	2
4	GAMS Options	3
5	Summary of GUROBI Options	3
5.1	Termination options	3
5.2	Tolerance options	4
5.3	Simplex and Barrier options	4
5.4	MIP options	4
5.5	Other options	5
5.6	The GAMS/Gurobi Options File	5
6	GAMS/Gurobi Log File	6
7	Detailed Descriptions of GUROBI Options	8

1 Introduction

The Gurobi suite of optimization products include state-of-the-art simplex and barrier based linear programming (LP) and mixed-integer programming (MIP) capability.

While numerous solving options are available, Gurobi automatically calculates and sets most options at the best values for specific problems. All Gurobi options available through GAMS/Gurobi are summarized at the end of this chapter.

2 How to Run a Model with Gurobi

The following statement can be used inside your GAMS program to specify using Gurobi

```
Option LP = Gurobi;      { or MIP or RMIP }
```

The above statement should appear before the `solve` statement. If Gurobi was specified as the default solver during GAMS installation, the above statement is not necessary.

3 Overview of GAMS/Gurobi

3.1 Linear Programming

Gurobi solves LP problems using several alternative algorithms. The majority of LP problems solve best using Gurobi's state of the art dual simplex algorithm. Certain types of problems benefit from using the barrier and the primal simplex algorithms.

GAMS/Gurobi also provides access to the Gurobi infeasibility finder. The infeasibility finder takes an infeasible linear program and produces an irreducibly inconsistent set of constraints (IIS). An IIS is a set of constraints and variable bounds which is infeasible but becomes feasible if any one member of the set is dropped. GAMS/Gurobi reports the IIS in terms of GAMS equation and variable names and includes the IIS report as part of the normal solution listing. The infeasibility finder is activated by the option `iis`.

GAMS/Gurobi supports sensitivity analysis (post-optimality analysis) for linear programs which allows one to find out more about an optimal solution for a problem. In particular, objective ranging and constraint ranging give information about how much an objective coefficient or a right-hand-side and variable bounds can change without changing the optimal basis. In other words, they give information about how sensitive the optimal basis is to a change in the objective function or the bounds and right-hand side. GAMS/Gurobi reports the sensitivity information as part of the normal solution listing. Sensitivity analysis is activated by the option `sensitivity`.

The Gurobi presolve can sometimes diagnose a problem as being infeasible *or* unbounded. When this happens, GAMS/Gurobi can, in order to get better diagnostic information, rerun the problem with presolve turned off. The rerun without presolve is controlled by the option `rerun`. In default mode only problems that are small (i.e. demo sized) will be rerun.

Gurobi can either presolve a model or start from an advanced basis. Often the solve from scratch of a presolved model outperforms a solve from an unpresolved model started from an advanced basis. It is impossible to determine a priori if presolve or starting from a given advanced basis without presolve will be faster. By default, GAMS/Gurobi will automatically use an advanced basis from a previous `solve` statement. The GAMS `BRatio` option can be used to specify when not to use an advanced basis. The GAMS/Gurobi option `usebasis` can be used to ignore a basis passed on by GAMS (it overrides `BRatio`). In case of multiple solves in a row and slow performance of the second and subsequent solves, the user is advised to set the GAMS `BRatio` option to 1.

3.2 Mixed-Integer Programming

The methods used to solve pure integer and mixed integer programming problems require dramatically more mathematical computation than those for similarly sized pure linear programs. Many relatively small integer programming models take enormous amounts of time to solve.

For problems with discrete variables, Gurobi uses a branch and cut algorithm which solves a series of LP subproblems. Because a single mixed integer problem generates many subproblems, even small mixed integer problems can be very compute intensive and require significant amounts of physical memory.

GAMS/Gurobi supports Special Order Sets of type 1 and type 2 as well as semi-continuous and semi-integer variables.

You can provide a known solution (for example, from a MIP problem previously solved or from your knowledge of the problem) to serve as the first integer solution.

If you specify some or all values for the discrete variables together with GAMS/Gurobi option `mipstart`, Gurobi will check the validity of the values as an integer-feasible solution. If this process succeeds, the solution will be treated as an integer solution of the current problem.

The Gurobi MIP solver includes shared memory parallelism, capable of simultaneously exploiting any number of processors and cores per processor. The implementation is deterministic: two separate runs on the same model will produce identical solution paths.

4 GAMS Options

The following GAMS options are used by GAMS/Gurobi:

Option BRatio = x;

Determines whether or not to use an advanced basis. A value of 1.0 causes GAMS to instruct Gurobi not to use an advanced basis. A value of 0.0 causes GAMS to construct a basis from whatever information is available. The default value of 0.25 will nearly always cause GAMS to pass along an advanced basis if a solve statement has previously been executed.

Option IterLim = n;

Sets the simplex iteration limit. Simplex algorithms will terminate and pass on the current solution to GAMS. For MIP problems, if the number of the cumulative simplex iterations exceeds the limit, Gurobi will terminate.

Option NodLim = x;

Maximum number of nodes to process for a MIP problem. This GAMS option is overridden by the GAMS/Gurobi option `nodelimit`.

Option OptCR = x;

Relative optimality criterion for a MIP problem. Notice that Gurobi uses a different definition than GAMS normally uses. The OptCR option asks Gurobi to stop when

$$|BP - BF| < |BF| * \text{OptCR}$$

where BF is the objective function value of the current best integer solution while BP is the best possible integer solution. The GAMS definition is:

$$|BP - BF| < |BP| * \text{OptCR}$$

Option ResLim = x;

Sets the time limit in seconds. The algorithm will terminate and pass on the current solution to GAMS. Gurobi measures time in wall time on all platforms. Some other GAMS solvers measure time in CPU time on some Unix systems. This GAMS option is overridden by the GAMS/Gurobi option `timelimit`.

Option SysOut = On;

Will echo Gurobi messages to the GAMS listing file. This option may be useful in case of a solver failure.

ModelName.Cutoff = x;

Cutoff value. When the branch and bound search starts, the parts of the tree with an objective worse than x are deleted. This can sometimes speed up the initial phase of the branch and bound algorithm. This GAMS option is overridden by the GAMS/Gurobi option `cutoff`.

ModelName.OptFile = 1;

Instructs GAMS/Gurobi to read the option file. The name of the option file is `gurobi.opt`.

5 Summary of GUROBI Options

5.1 Termination options

<code>bariterlimit</code>	Limits the number of barrier iterations performed
<code>cutoff</code>	Sets a target objective value

iterationlimit	Limits the number of simplex iterations performed
nodelimit	Limits the number of MIP nodes explored
solutionlimit	Limits the number of feasible solutions found
timelimit	Limits the total time expended in seconds

5.2 Tolerance options

barconvtol	Controls barrier termination
feasibilitytol	Primal feasibility tolerance
intfeastol	Integer feasibility tolerance
markowitztol	Threshold pivoting tolerance
mipgap	Relative MIP optimality gap
mipgapabs	Absolute MIP optimality gap
optimalitytol	Dual feasibility tolerance

5.3 Simplex and Barrier options

barcorrectors	Limits the number of central corrections performed in each barrier iteration
barorder	Chooses the barrier sparse matrix fill-reducing algorithm
crossover	Determines the crossover strategy used to transform the barrier solution into a basic solution
crossoverbasis	Determines the initial basis construction strategy for crossover
lpmethod	LP algorithm
normadjust	Pricing norm variants
objscale	Objective coefficients scaling
perturbvalue	Magnitude of simplex perturbation when required
quad	Quad precision computation in simplex
scaleflag	Enables or disables model scaling
simplexpricing	Determines variable pricing strategy

5.4 MIP options

cliquecuts	Controls clique cut generation
covercuts	Controls cover cut generation
cutaggpases	Maximum number of aggregation passes during cut generation
cuts	Global cut generation control
flowcovercuts	Controls flow cover cut generation
flowpathcuts	Controls flow path cut generation
gomorypasses	Maximum number of Gomory cut passes
gubcovercuts	Controls GUB cover cut generation
heuristics	Controls the amount of time spent in MIP heuristics
impliedcuts	Controls implied bound cut generation
mipfocus	Controls the focus of the MIP solver
mipsecuts	Controls MIP separation cut generation
mircuts	Controls MIR cut generation
networkcuts	Controls network cut generation
nodefiledir	Nodefile directory
nodefilestart	Nodefile starting indicator
pumppasses	Number of passes of the feasibility pump heuristic

<code>rins</code>	Frequency of the RINS heuristic
<code>rootmethod</code>	LP algorithm used for MIP root relaxation
<code>submipcuts</code>	Controls the generation of sub-MIP cutting planes
<code>submipnodes</code>	Limits the number of nodes explored by the heuristics
<code>symmetry</code>	Controls MIP symmetry detection
<code>varbranch</code>	Controls the branch variable selection strategy
<code>zerohalfcuts</code>	Controls zero-half cut generation

5.5 Other options

<code>aggregate</code>	Enables or disables aggregation in presolve
<code>aggfill</code>	Controls the amount of fill allowed during presolve aggregation
<code>displayinternal</code>	Controls the frequency at which log lines are printed in seconds
<code>dumpsolution</code>	Controls export of alternate MIP solutions
<code>fixoptfile</code>	Option file for fixed problem optimization
<code>iis</code>	Run the IIS finder if the problem is infeasible
<code>iismethod</code>	Controls use of IIS method
<code>kappa</code>	Display condition number of the basis matrix
<code>mipstart</code>	Use mip starting values
<code>names</code>	Indicator for loading names
<code>precrush</code>	Presolve constraint option
<code>predual</code>	Controls whether presolve forms the dual of a continuous model
<code>predeprow</code>	Controls the presolve dependent row reduction
<code>prepasses</code>	Controls the number of passes performed by presolve
<code>presolve</code>	Controls the presolve level
<code>printoptions</code>	List values of all options to GAMS listing file
<code>readparams</code>	Read Gurobi parameter file
<code>rerun</code>	Resolve without presolve in case of unbounded or infeasible
<code>sensitivity</code>	Provide sensitivity information
<code>solvefixed</code>	Indicator for solving the fixed problem for a MIP to get a dual solution
<code>threads</code>	Controls the number of threads to apply to parallel MIP or Barrier
<code>usebasis</code>	Use basis from GAMS
<code>writeparams</code>	Write Gurobi parameter file
<code>writeprob</code>	Save the problem instance

5.6 The GAMS/Gurobi Options File

The GAMS/Gurobi options file consists of one option or comment per line. An asterisk (*) at the beginning of a line causes the entire line to be ignored. Otherwise, the line will be interpreted as an option name and value separated by any amount of white space (blanks or tabs).

Following is an example options file *gurobi.opt*.

```
simplexpricing 3
lpmethod 0
```

It will cause Gurobi to use quick-start steepest edge pricing and will use the primal simplex algorithm.

6 GAMS/Gurobi Log File

Gurobi reports its progress by writing to the GAMS log file as the problem solves. Normally the GAMS log file is directed to the computer screen.

The log file shows statistics about the presolve and continues with an iteration log.

For the simplex algorithms, each log line starts with the iteration number, followed by the objective value, the primal and dual infeasibility values, and the elapsed wall clock time. The dual simplex uses a bigM approach for handling infeasibility, so the objective and primal infeasibility values can both be very large during phase I. The frequency at which log lines are printed is controlled by the *displayinterval* option. By default, the simplex algorithms print a log line roughly every five seconds, although log lines can be delayed when solving models with particularly expensive iterations.

The simplex screen log has the following appearance:

```
Presolve removed 977 rows and 1539 columns
Presolve changed 3 inequalities to equalities
Presolve time: 0.078000 sec.
Presolved: 1748 Rows, 5030 Columns, 32973 Nonzeros
```

Iteration	Objective	Primal Inf.	Dual Inf.	Time
0	3.8929476e+31	1.200000e+31	1.485042e-04	0s
5624	1.1486966e+05	0.000000e+00	0.000000e+00	2s

```
Solved in 5624 iterations and 1.69 seconds
Optimal objective 1.148696610e+05
```

For the barrier algorithm, it starts with barrier statistics about dense columns, free variables, nonzeros in AA' and Cholesky factor, computational operations needed for the factorization, memory estimate and time estimate per iteration. Then it outputs the progress of the barrier algorithm in iterations with the primal and dual objective values, the magnitude of the primal and dual infeasibilities and the magnitude of the complementarity violation. After the barrier algorithm terminates, by default, Gurobi will perform crossover to obtain a valid basic solution, it first prints the information about pushing the dual and primal superbasic variables to the bounds and then the information about the simplex progress until the completion of the optimization.

The barrier screen log has the following appearance:

```
Presolve removed 2394 rows and 3412 columns
Presolve time: 0.09s
Presolved: 3677 Rows, 8818 Columns, 30934 Nonzeros
```

```
Ordering time: 0.20s
```

Barrier statistics:

```
Dense cols : 10
Free vars  : 3
AA' NZ     : 9.353e+04
Factor NZ  : 1.139e+06 (roughly 14 MBytes of memory)
Factor Ops : 7.388e+08 (roughly 2 seconds per iteration)
```

Iter	Objective		Residual		Compl	Time
	Primal	Dual	Primal	Dual		
0	1.11502515e+13	-3.03102251e+08	7.65e+05	9.29e+07	2.68e+09	2s
1	4.40523949e+12	-8.22101865e+09	3.10e+05	4.82e+07	1.15e+09	3s
2	1.18016996e+12	-2.25095257e+10	7.39e+04	1.15e+07	3.37e+08	4s
3	2.24969338e+11	-2.09167762e+10	1.01e+04	2.16e+06	5.51e+07	5s
4	4.63336675e+10	-1.44308755e+10	8.13e+02	4.30e+05	9.09e+06	6s

5	1.25266057e+10	-4.06364070e+09	1.52e+02	8.13e+04	2.21e+06	7s
6	1.53128732e+09	-1.27023188e+09	9.52e+00	1.61e+04	3.23e+05	9s
7	5.70973983e+08	-8.11694302e+08	2.10e+00	5.99e+03	1.53e+05	10s
8	2.91659869e+08	-4.77256823e+08	5.89e-01	5.96e-08	8.36e+04	11s
9	1.22358325e+08	-1.30263121e+08	6.09e-02	7.36e-07	2.73e+04	12s
10	6.47115867e+07	-4.50505785e+07	1.96e-02	1.43e-06	1.18e+04	13s
.....						
26	1.12663966e+07	1.12663950e+07	1.85e-07	2.82e-06	1.74e-04	2s
27	1.12663961e+07	1.12663960e+07	3.87e-08	2.02e-07	8.46e-06	2s

Barrier solved model in 27 iterations and 1.86 seconds
 Optimal objective 1.12663961e+07

Crossover log...

1592 DPushes remaining with DInf 0.0000000e+00 2s
 0 DPushes remaining with DInf 2.8167333e-06 2s

180 PPushes remaining with PInf 0.0000000e+00 2s
 0 PPushes remaining with PInf 0.0000000e+00 2s

Push phase complete: Pinf 0.0000000e+00, Dinf 2.8167333e-06 2s

Iteration	Objective	Primal Inf.	Dual Inf.	Time
1776	1.1266396e+07	0.000000e+00	0.000000e+00	2s

Solved in 2043 iterations and 2.00 seconds
 Optimal objective 1.126639605e+07

For MIP problems, the Gurobi solver prints regular status information during the branch and bound search. The first two output columns in each log line show the number of nodes that have been explored so far in the search tree, followed by the number of nodes that remain unexplored. The next three columns provide information on the most recently explored node in the tree. The solver prints the relaxation objective value for this node, followed by its depth in the search tree, followed by the number of integer variables with fractional values in the node relaxation solution. The next three columns provide information on the progress of the global MIP bounds. They show the objective value for the best known integer feasible solution, the best bound on the value of the optimal solution, and the gap between these lower and upper bounds. Finally, the last two columns provide information on the amount of work performed so far. The first column gives the average number of simplex iterations per explored node, and the next column gives the elapsed wall clock time since the optimization began.

At the default value for option *displayinterval*), the MIP solver prints one log line roughly every five seconds. Note, however, that log lines are often delayed in the MIP solver due to particularly expensive nodes or heuristics.

Presolve removed 12 rows and 11 columns
 Presolve tightened 70 bounds and modified 235 coefficients
 Presolve time: 0.02s
 Presolved: 114 Rows, 116 Columns, 424 Nonzeros
 Objective GCD is 1

Nodes		Current Node			Objective Bounds			Work	
Expl	Unexpl	Obj	Depth	IntInf	Incumbent	BestBd	Gap	It/Node	Time
H	0	0			-0.0000	-	-	-	0s
Root relaxation: 208 iterations, 0.00 seconds									
	0	0	29.6862	0 64	-0.0000	29.6862	-	-	0s
H	0	0			8.0000	29.6862	271%	-	0s
H	0	0			17.0000	29.6862	74.6%	-	0s

	0	2	27.4079	0	60	17.0000	27.4079	61.2%	-	0s
H	27	17				18.0000	26.0300	44.6%	51.6	0s
*	87	26		45		20.0000	26.0300	30.2%	28.4	0s
*	353	71		29		21.0000	25.0000	19.0%	19.3	0s
	1268	225	24.0000	28	43	21.0000	24.0000	14.3%	32.3	5s
	2215	464	22.0000	43	30	21.0000	24.0000	14.3%	33.2	10s

Cutting planes:

Gomory: 175

Cover: 25

Implied bound: 87

MIR: 150

Explored 2550 nodes (84600 simplex iterations) in 11.67 seconds

Thread count was 1 (of 4 available processors)

Optimal solution found (tolerance 1.00e-01)

Best objective 2.1000000000e+01, best bound 2.3000000000e+01, gap 9.5238%

7 Detailed Descriptions of GUROBI Options

aggregate (*integer*) Enables or disables aggregation in presolve

(default = 1)

aggfill (*integer*) Controls the amount of fill allowed during presolve aggregation

Larger values generally lead to presolved models with fewer rows and columns, but with more constraint matrix non-zeros.

(default = 10)

bariterlimit (*integer*) Limits the number of barrier iterations performed

(default = infinity)

barconvtol (*real*) Controls barrier termination

The barrier solver terminates when the relative difference between the primal and dual objective values is less than the specified tolerance.

(default = 1e-8)

barcorrectors (*integer*) Limits the number of central corrections performed in each barrier iteration

The default value is chosen automatically, depending on problem characteristics.

(default = -1)

barorder (*integer*) Chooses the barrier sparse matrix fill-reducing algorithm

(default = -1)

-1 Auto

0 Approximate Minimum Degree ordering

1 Nested Dissection ordering

cliquecuts (*integer*) Controls clique cut generation

See the description of the global [Cuts](#) parameter for further information.

(default = -1)

-1 Auto

- 0 Off
- 1 Conservative
- 2 Aggressive

covercuts (*integer*) Controls cover cut generation

See the description of the global [Cuts](#) parameter for further information.

(*default = -1*)

- 1 Auto
- 0 Off
- 1 Conservative
- 2 Aggressive

crossover (*integer*) Determines the crossover strategy used to transform the barrier solution into a basic solution

Use value 0 to disable crossover; the solver will return an interior solution. Other options control whether the crossover algorithm tries to push primal or dual variables to bounds first, and then which simplex algorithm is used once variable pushing is complete. Options 1 and 2 push dual variables first, then primal variables. Option 1 finishes with primal, while option 2 finishes with dual. Options 3 and 4 push primal variables first, then dual variables. Option 3 finishes with primal, while option 4 finishes with dual. The default value of -1 chooses automatically.

(*default = -1*)

crossoverbasis (*integer*) Determines the initial basis construction strategy for crossover

The default value (0) chooses an initial basis quickly. A value of 1 can take much longer, but often produces a much more numerically stable start basis.

(*default = 0*)

cutaggpases (*integer*) Maximum number of aggregation passes during cut generation

A non-negative value indicates the maximum number of constraint aggregation passes performed during cut generation. See the description of the global [Cuts](#) parameter for further information.

(*default = -1*)

cutoff (*real*) Sets a target objective value

Optimization will terminate if the engine determines that the optimal objective value for the model is worse than the specified cutoff. This option overwrites the GAMS cutoff option.

(*default = 0*)

cuts (*integer*) Global cut generation control

The parameters, [cuts](#), [cliquecuts](#), [covercuts](#), [flowcovercuts](#), [flowpathcuts](#), [gubcovercuts](#), [impliedcuts](#), [mipsep-cuts](#), [mircuts](#), [networkcuts](#), [gomorypasses](#), [submipcuts](#), [cutaggpases](#) and [zerohalfcuts](#), affect the generation of MIP cutting planes. In all cases except [gomorypasses](#) and [cutaggpases](#), a value of -1 corresponds to an automatic setting, which allows the solver to determine the appropriate level of aggressiveness in the cut generation. Unless otherwise noted, settings of 0, 1, and 2 correspond to no cut generation, conservative cut generation, or aggressive cut generation, respectively. The [Cuts](#) parameter provides global cut control, affecting the generation of all cuts. This parameter also has a setting of 3, which corresponds to very aggressive cut generation. The other parameters override the global [Cuts](#) parameter (so setting [Cuts](#) to 2 and [CliqueCuts](#) to 0 would generate all cut types aggressively, except clique cuts which would not be generated at all. Setting [Cuts](#) to 0 and [Gomorypasses](#) to 10 would not generate any cuts except Gomory cuts for 10 passes).

(*default = -1*)

- 1 Auto

- 0 Off
- 1 Conservative
- 2 Aggressive
- 3 Very aggressive

displayinternal (*integer*) Controls the frequency at which log lines are printed in seconds
(*default = 5*)

dumpsolution (*string*) Controls export of alternate MIP solutions

The GDX file specified by this option will contain a set call `index` that contains the names of GDX files with the individual solutions. For details see example model `dumpsol` in the GAMS Test Library.

feasibilitytol (*real*) Primal feasibility tolerance

All constraints must be satisfied to a tolerance of *FeasibilityTol*.

Range: $[1e-9, 1e-2]$

(*default = 1e-6*)

fixoptfile (*string*) Option file for fixed problem optimization

flowcovercuts (*integer*) Controls flow cover cut generation

See the description of the global [Cuts](#) parameter for further information.

(*default = -1*)

- 1 Auto
- 0 Off
- 1 Conservative
- 2 Aggressive

flowpathcuts (*integer*) Controls flow path cut generation

See the description of the global [Cuts](#) parameter for further information.

(*default = -1*)

- 1 Auto
- 0 Off
- 1 Conservative
- 2 Aggressive

gomorypasses (*integer*) Maximum number of Gomory cut passes

A non-negative value indicates the maximum number of Gomory cut passes performed. See the description of the global [Cuts](#) parameter for further information.

(*default = -1*)

gubcovercuts (*integer*) Controls GUB cover cut generation

See the description of the global [Cuts](#) parameter for further information.

(*default = -1*)

- 1 Auto
- 0 Off
- 1 Conservative
- 2 Aggressive

heuristics (*real*) Controls the amount of time spent in MIP heuristics

Larger values produce more and better feasible solutions, at a cost of slower progress in the best bound.

Range: $[0,1]$

(default = 0.05)

iis (*integer*) Run the IIS finder if the problem is infeasible

(default = 0)

iismethod (*integer*) Controls use of IIS method

Chooses the IIS method to use. Method 0 is often faster, while method 1 can produce a smaller IIS. The default value of -1 chooses automatically.

(default = -1)

impliedcuts (*integer*) Controls implied bound cut generation

See the description of the global [Cuts](#) parameter for further information.

(default = -1)

-1 Auto

0 Off

1 Conservative

2 Aggressive

intfeastol (*real*) Integer feasibility tolerance

An integrality restriction on a variable is considered satisfied when the variable's value is less than *IntFeasTol* from the nearest integer value.

Range: $[1e-9,1e-1]$

(default = 1e-5)

iterationlimit (*real*) Limits the number of simplex iterations performed

(default = infinity)

kappa (*integer*) Display condition number of the basis matrix

(default = 0)

lpmethod (*integer*) LP algorithm

(default = 1)

0 Primal simplex

1 Dual simplex

2 Barrier

markowitztol (*real*) Threshold pivoting tolerance

Used to limit numerical error in the simplex algorithm. A larger value may avoid numerical problems in rare situations, but it will also harm performance.

Range: $[1e-4,0.999]$

(default = 0.0078125)

mipfocus (*integer*) Controls the focus of the MIP solver

(default = 0)

0 Balance between finding good feasible solutions and proving optimality

1 Focus towards finding feasible solutions simplex

- 2 Focus towards proving optimality
- 3 Focus on moving the best objective bound

mipgap (*real*) Relative MIP optimality gap

The MIP engine will terminate (with an optimal result) when the gap between the lower and upper objective bound is less than *MipGap* times the upper bound.

Range: $[0, \text{maxdouble}]$

(default = GAMS optcr)

mipgapabs (*real*) Absolute MIP optimality gap

The MIP solver will terminate (with an optimal result) when the gap between the lower and upper objective bound is less than *MIPGapAbs*.

Range: $[0, \text{maxdouble}]$

(default = GAMS optca)

mipsepcuts (*integer*) Controls MIP separation cut generation

See the description of the global [Cuts](#) parameter for further information.

(default = -1)

- 1 Auto
- 0 Off
- 1 Conservative
- 2 Aggressive

mipstart (*integer*) Use mip starting values

(default = 0)

mircuts (*integer*) Controls MIR cut generation

See the description of the global [Cuts](#) parameter for further information.

(default = -1)

- 1 Auto
- 0 Off
- 1 Conservative
- 2 Aggressive

networkcuts (*integer*) Controls network cut generation

See the description of the global [Cuts](#) parameter for further information.

(default = -1)

- 1 Auto
- 0 Off
- 1 Conservative
- 2 Aggressive

names (*integer*) Indicator for loading names

(default = 1)

nodefiledir (*string*) Nodefile directory

Determines the directory into which nodes are written when node memory usage exceeds the specified NodefileStart value.

(default = .)

nodefilestart (*real*) Nodefile starting indicator

Controls the point at which MIP tree nodes are written to disk. Whenever node storage exceeds the specified value (in GBytes), nodes are written to disk.

(default = *maxdouble*)

nodelimit (*real*) Limits the number of MIP nodes explored

(default = *maxdouble*)

normadjust (*integer*) Pricing norm variants

Chooses from among multiple pricing norm variants. The default value of -1 chooses automatically.

(default = -1)

objscale (*real*) Objective coefficients scaling

Divides the model objective by the specified value to avoid numerical errors that may result from very large objective coefficients. The default value of 0 decides on the scaling automatically. A value less than zero uses the maximum coefficient to the specified power as the scaling (so *ObjScale*=-0.5 would scale by the square root of the largest objective coefficient).

Range: [-1,*maxdouble*]

(default = 0)

optimalitytol (*real*) Dual feasibility tolerance

Reduced costs must all be larger than *OptimalityTol* in the improving direction in order for a model to be declared optimal.

Range: [1e-9,1e-2]

(default = 1e-6)

perturbvalue (*real*) Magnitude of simplex perturbation when required

Range: [0,0.01]

(default = 0.0002)

precrush (*integer*) Presolve constraint option

Allows presolve to translate constraints on the original model to equivalent constraints on the presolved model. This parameter is turned on when you use BCH with Gurobi.

(default = 0)

predual (*integer*) Controls whether presolve forms the dual of a continuous model

Depending on the structure of the model, solving the dual can reduce overall solution time. The default setting uses a heuristic to decide. Setting 0 forbids presolve from forming the dual, while setting 1 forces it to take the dual. Setting 2 employs a more expensive heuristic that forms both the presolved primal and dual models (on two threads), and heuristically chooses one of them.

(default = -1)

predeprop (*integer*) Controls the presolve dependent row reduction

Controls the presolve dependent row reduction, which eliminates linearly dependent constraints from the constraint matrix. The default setting (-1) applies the reduction to continuous models but not to MIP models. Setting 0 turns the reduction off for all models. Setting 1 turns it on for all models.

(default = -1)

prepasses (*integer*) Controls the number of passes performed by presolve

Limits the number of passes performed by presolve. The default setting (-1) chooses the number of passes automatically.

(default = -1)

presolve (*integer*) Controls the presolve level

(default = -1)

- 1 Auto
- 0 Off
- 1 Conservative
- 2 Aggressive

printhoptions (*integer*) List values of all options to GAMS listing file

(default = 0)

pumppasses (*integer*) Number of passes of the feasibility pump heuristic

Note that this heuristic is only applied at the end of the MIP root, and only when no other root heuristic found a feasible solution.

(default = 0)

quad (*integer*) Quad precision computation in simplex

Enables or disables quad precision computation in simplex. The -1 default setting allows the algorithm to decide.

(default = -1)

readparams (*string*) Read Gurobi parameter file

rerun (*integer*) Resolve without presolve in case of unbounded or infeasible

In case Gurobi reports *Model was proven to be either infeasible or unbounded*, this option decides about a resolve without presolve which will determine the exact model status. If the option is set to *auto*, which is the default, and the model fits into demo limits, the problem is resolved.

(default = 0)

- 1 No
- 0 Auto
- 1 Yes

rins (*integer*) Frequency of the RINS heuristic

Default value (-1) chooses automatically. A value of 0 shuts off RINS. A positive value n applies RINS at every n -th node of the MIP search tree.

(default = -1)

rootmethod (*integer*) LP algorithm used for MIP root relaxation

(default = 1)

- 0 Primal
- 1 Dual
- 2 Barrier

scaleflag (*integer*) Enables or disables model scaling

(default = 1)

sensitivity (*integer*) Provide sensitivity information

(default = 0)

simplexpricing (*integer*) Determines variable pricing strategy

(default = -1)

- 1 Auto
- 0 Partial Pricing
- 1 Steepest Edge
- 2 Devex
- 3 Quick-Start Steepest Edge

solutionlimit (*integer*) Limits the number of feasible solutions found
(default = *maxint*)

solvefixed (*integer*) Indicator for solving the fixed problem for a MIP to get a dual solution
(default = 1)

submipcuts (*integer*) Controls the generation of sub-MIP cutting planes
See the description of the global [Cuts](#) parameter for further information.
(default = -1)

submipnodes (*integer*) Limits the number of nodes explored by the heuristics
Limits the number of nodes explored by the heuristics, like RINS. Exploring more nodes can produce better solutions, but it generally takes longer.
(default = 500)

symmetry (*integer*) Controls MIP symmetry detection
(default = -1)

- 1 Auto
- 0 Off
- 1 Conservative
- 2 Aggressive

threads (*integer*) Controls the number of threads to apply to parallel MIP or Barrier
Default number of parallel threads allowed for any solution method. Non-positive values are interpreted as the number of cores to leave free so setting threads to 0 uses all available cores while setting threads to -1 leaves one core free for other tasks.
(default = 1)

timelimit (*real*) Limits the total time expended in seconds
(default = *GAMS reslim*)

usebasis (*integer*) Use basis from GAMS
(default = 0)

varbranch (*integer*) Controls the branch variable selection strategy
(default = -1)

- 1 Auto
- 0 Pseudo Reduced Cost Branching
- 1 Pseudo Shadow Price Branching
- 2 Maximum Infeasibility Branching
- 3 Strong Branching

writeparams (*string*) Write Gurobi parameter file

writeprob (*string*) Save the problem instance

zerohalfcuts (*integer*) Controls zero-half cut generation

See the description of the global [Cuts](#) parameter for further information.

(*default = -1*)

-1 Auto

0 Off

1 Conservative

2 Aggressive